
Regarding the free version upgrade for GateWT

GateWT の無償レビジョンアップのご案内

Thank you for using the DAQWORX Data Acquisition Software Suite. Please note the following when connecting the WT1800 or WT500 to GateWT (Model code : WX1). Please read the following description before proceeding.

To relevant customers

For customers connecting the WT1800 to GateWT, or using the WT500's Ethernet communications:

Precautions

WT1800 and WT500 communications are not supported with installations of GateWT R2.05.01 recorded on DAQWORX R2.09.01 or earlier. Support for these products and their functions can be added by upgrading GateWT.

Download the upgrade and user's manual

Please download the upgrade and user's manual from the following Web page.

Web page URL:

<http://www.yokogawa.com/ns/gatewt/download/>

Installing and verifying the upgrade

After installing GateWT, install the upgrade. Installing the upgrade does not affect your existing GateWT settings. Click the About button on the tool bar or choose Help > About from the menu bar. Confirm that the GateWT version is R2.06.01.

データ収集システム統合ソフトウェア DAQWORX をご利用いただき、誠にありがとうございます。
GateWT (形名 : WX1) に WT1800 または WT500 を接続する場合に、ご注意ください点がございます。
お手数をかけますが、以下の説明をご一読の上、対応くださいますようお願いいたします。

対象となるお客様

GateWT に WT1800 を接続する、または WT500 の Ethernet 通信を使用するお客様。

ご注意ください内容

DAQWORX R2.09.01 に収録されている GateWT R2.05.01 またはそれ以前のバージョンでは、WT1800、および WT500 の Ethernet 通信には対応していません。GateWT のアップグレード版を適用することにより、これらの製品と機能に対応できるようになります。

アップグレード版と取扱説明書のダウンロード

下記の Web ページからアップグレード版と取扱説明書をダウンロードしてください。

Web ページ URL

<http://www.yokogawa.co.jp/ns/gatewt/download/>

アップグレード版の適用と確認

GateWT をインストールした後に、アップグレード版を適用してください。アップグレード版を適用しても、GateWT の既存の環境設定は保持されます。

ツールバーの「バージョン情報」ボタンをクリックするか、メニューバーのヘルプ > バージョン情報を選択します。GateWT のバージョンが R2.06.01 と表示されることを確認してください。